

2014 Debit Wallets - SNAP
 by Sherry Titzer
<http://www.atimetostitch.com>

List of supplies & cutting instructions provided with orders. Project fits 5x7 or larger hoops to make wallet in the hoop except for the final top stitching! Just follow the steps in the order listed below!

STEP 1 – DEBIT CARD SLEEVE ENSEMBLE



1. On the sleeve pieces, fuse 4" strip of Heat 'n Bond tape even with edge on both 4 1/2" sides on all four sleeve pieces.

1. On one edge, fold at inside edge of tape & iron to crease fabric. Remove paper backing, iron to fuse fold on all sleeves.




3. On Sleeve Base Front - mark faint lines across the width of the fabric 2 3/4" in from both ends.

4. Remove paper backing from sleeve bottoms. Place folded edge of 2 sleeves at the 2 3/4" marks and iron to fuse the bottom. Next, place raw edge of last 2 sleeves even with ends of base fabric and iron to fuse as well.




5. On wrong side of Base BACK fabric, center strip of fusible tape on one long side even with the edge. Place BACK fabric wrong side up over sleeve ensemble even with right side. Stitch with 3/8" seam.

6. Flip fabric around flat seam to create a bound edge. Top stitch bound edge & also the other side to secure sleeves with 1/4" seam.



7. Flip ensemble over and mark center on the unfinished edge.


STEP 2 – TAB CLOSURE (with snap)



8. Tab closure – stitch placement line on stabilizer.



9. Center fabric inside outline & stitch design.



10. Center interfaced fabric wrong side up over fabric in hoop. The last step stitches front/back together.



11. Trim to 1/4" seams & notch corners for turning. Turn right side out & press. Top stitch sides and angled bottom with 1/4" seam. DO NOT INSTALL SNAP YET!


STEP 3 - WALLET



12. LINING – On wrong side add fusible interfacing centered and even with 1 edge. Add fusible tape to other edge.




13. CASE - Center fusible fleece on wrong side of case fabric. Next, center fusible interfacing over the fleece. (graduated sizes to reduce bulk on finished wallet)



14. On right side of case fabric, mark center on both 5 1/2" wide sides close to the edge. (2 3/4" is center)



15. Mark cross mark (+) at one end of case fabric and install half of the snap. (snapping part of snap on right side of fabric.)



16. Stitch placement lines on stabilizer. Extend ALL of the vertical lines ~3/4" longer at the top & bottom. Make the center line on the right side 3/4" longer as well.



17. Spray stabilizer with temporary adhesive spray. Place fabric in hoop (snap at top) even with top placement line keeping center marks on fabric & stabilizer even. Stitch design using instructions in text file.

NOTE: For 5x7 hoops, mark an extra horizontal line 1/4" above the stitched horizontal placement line at the top.
This was the only way I could get the design fit the 5x7 hoop!




(Print fabric for wallet was used so you can see where to place the tab closure better!)

18. When instructed, remove hoop and center tab closure wrong side up even with bottom of fabric in hoop. Use marked lines to center. Tape tab at the sides to secure.



19. Next, center SLEEVE ensemble wrong side up keeping bound edge even with vertical placement marks on the left side and center mark on back of ensemble even with horizontal center line marked on the stabilizer earlier. Tape corners to secure.



20. Next, center LINING wrong side up even with left edge of fabric in hoop. Lining is narrower to leave opening for turning. Tape corners. Last step - stitches case outline.

21. Remove ensemble from the hoop. Trim all of the sides to 1/4" seams to reduce bulk. Trim fabric at corners at an angle for turning

22. Remove paper backing from fusible tape on lining and turn right side out through opening in lining. Maneuver until all seams are even at edges & lining is flat under debit card ensemble. Iron to set the edges. Top stitch around edge of wallet with 1/4" seam. Install other half of snap on the tab closure. You're finished!



FRONT VIEW



BACK VIEW



Holds 4 debit/or credit cards or driver's license. Has pocket to store money, coupons or receipts.